

COBTEST Development Tool

Mainframe courses at SYS-ED include:

- | | |
|---|--|
| • Programming Skills | • Programming Languages |
| • PC Emulation of Mainframe Software | • Utilities & Development Tools |
| • Telecommunications | • Operating Systems |
| • VSAM | • CICS |
| • Database: IMS | • Relational Database |
| • Client/Server for MVS | • Productivity Management |

To see a list of courses available, go to our web site at www.sysed.com.

*Get on the
Fast Track!*



TM

| | |
|--|---|
| AT [ENTRY program,...][ALL] [statement[statement1:statement2] [(command-list)] [COUNT(n[,m[,k]]) NOTIFY[NONOTIFY] [DEFER] | Function: Establishes breakpoint at one or more COBOL verbs Abbreviation: A Modes: Batch, Line or Full Screen |
| AUTO [LIST command [ON [OFF] | Function: Starts automatic listing of program variables Abbreviation: AU Modes: Full Screen |
| COLOR | Function: Tailor the color attributes of the full screen display. Abbreviation: COL Modes: Full Screen |
| * comments | Function: Provide comments in the debugging session. Abbreviation: None Modes: Batch, Line, or Full Screen |
| DROP[symbol,...] | Function: Deletes a symbolpoint at one or more COBOL verbs Abbreviation: A Modes: Batch, Line or Full Screen |
| DUMP | Function: Terminates session and writes a dump to the SYSABOUT (MVS/TSO), CICS dump data set or CMS virtual printer. Abbreviation: DU Modes: Batch, Line or Full Screen |
| FLOW [ON OFF PRINT] (n) PRINT] | Function: Traces the flow of control in your program. Abbreviation: FL Modes: Batch, Line or Full Screen |
| FREQ [ALL program] (program,...)] [OFF] | Function: Turns on statement frequency tallying. Abbreviation: FR Mode: FRModes: Batch, Line or Full Screen. |
| GO [Statement] | Function: Starts or resumes execution. Abbreviation: G Modes: Batch, Line or Full Screen |
| HELP [Command] [ALL FUNCTION OPERANDS[(operand list)] SYNTAX] | Function: Provides information regarding a COBTEST command. Abbreviation: G Modes: Line or Full Screen |
| IF (expression) [(command list)] HALT HA GO | Function: Provides for conditional executin of debug commands. Abbreviation: I Modes: Batch, Line or Full Screen |
| LINK [USING data-item [,data-item,...]] | Function: Simulate the execution of a subprogram. Abbreviation: LIN Modes: Batch, Line or Full Screen |



| | |
|---|--|
| <p>LIST [item,item,... ALL literal [GROUP] [DISPLAY BOTH HEX] [PRINT]</p> <p>Function: Displays or prints the attributes and values of selected fields. Abbreviation: L Modes: Batch, Line or Full Screen</p> | <p>PREVDISP</p> <p>Function: Redisplays the previous panel. Abbreviation: PREV Modes: Full Screen</p> |
| <p>LISTBRKS [PRINT]</p> <p>Function: Displays or prints the active breakpoints. Abbreviation: LISTB Modes: Batch, Line or Full Screen</p> | <p>PRINTDD ddname</p> <p>Function: Output ddname for the PRINT clause and the RECORD command. Abbreviation: PRI Modes: Batch, Line or Full</p> |
| <p>LISTEQ [PRINT]</p> <p>Function: Displays or prints the active symbols specified in an EQUATE command. Abbreviation: LISTE Modes: Batch, Line or Full Screen</p> | <p>PROFILE</p> <p>Function: Displays the profile panel. Abbreviation: PROF Modes: Full Screen</p> |
| <p>LISTFREQ [ALL program[,program...]] [ZEROFREQ] [PRINT]</p> <p>Function: Displays or prints the number of times each COBOL verb is executed. Abbreviation: LISTF Modes: Batch, Line or Full Screen</p> | <p>PROC</p> <p>Function: Simulates a non-existent subroutine. Abbreviation: PRO Modes: Full Screen</p> |
| <p>LISTINGS</p> <p>Function: Invokes the listing panel. Abbreviation: LISTI Modes: Full Screen</p> | <p>QUALIFY program</p> <p>Function: Provide all subsequent command with the program name qualification. Abbreviation: Q Modes: Batch, Line or Full Screen</p> |
| <p>MOVECURS</p> <p>Function: Moves the cursor between home and last position. Abbreviation: MOVEC, MC Modes: Full Screen</p> | <p>QUIT</p> <p>Function: Terminates session without a dump. Abbreviation: QUI Modes: Batch, Line or Full Screen</p> |
| <p>NEXT [(command list)]</p> <p>Function: Set a temporary breakpoint at the next verb. Abbreviation: N Modes: Batch, Line or Full Screen</p> | <p>RECORD NORECORD</p> <p>Function: Activates/deactivates logging. Abbreviation: RE NORE Modes: Batch, Line or Full Screen</p> |
| <p>OFF [statement[,statement...]] [statement1:statement2 [,statement1:statement2...]]</p> <p>Function: Remove breakpoint(s). Abbreviation: O (Full Screen only) Modes: Batch, Line or Full Screen</p> | <p>RESTART</p> <p>Function: Restarts and reloads program. Abbreviation: RESTA Modes: Line or Full Screen</p> |
| <p>OFFWN [when-name[,when-name...]]</p> <p>Function: Remove a conditional breakpoint established by a WHEN. Abbreviation: OFFW Modes: Batch, Line or Full Screen</p> | <p>RESTORE</p> <p>Function: Restores full screen to the last point of execution. Abbreviation: RESTO Modes: Full Screen</p> |
| <p>ONABEND [(command-list)]</p> <p>Function: If an ABEND occurs, execute the commands in the command list. Abbreviation: ONAB Modes: Batch, Line or Full Screen</p> | <p>RUN [statement]</p> <p>Function: Turns off debugging commands (ie: breakpoints) and executes the program. Abbreviation: R Modes: Batch, Line or Full Screen</p> |
| <p>PEEK</p> <p>Function: Allows viewing of the line numbers that are not displayed by the breakpoint feedback. Abbreviation: P Modes: Full Screen</p> | <p>SEARCH [delimited string]</p> <p>Function: Search for a character string. Abbreviation: SEA Modes: Full Screen</p> |
| <p>POSITION number</p> <p>Function: Places the specified line number on the top of the screen. Abbreviation: POS Modes: Full Screen</p> | <p>S number</p> <p>Function: Display a frequency count on a specific line with multiple verbs. Abbreviation: None Modes: Full Screen</p> |
| | <p>SET item1=[item2 literal]</p> <p>Function: Move a value into a data item. Abbreviation: S Modes: Batch, Line or Full Screen</p> |
| | <p>SOURCE [LISTING program L program OFF ON]</p> <p>Function: Open, closes, or changes the size of the source. Abbreviation: SO Modes: Full Screen</p> |

CALL
212-564-9147

CLICK
www.sysed.com

FAX
212-967-3498

US Headquarters
19 West 34th Street New York, NY 10001-3006



| |
|--|
| STEP number |
| Function: Executes a specified number of COBOL verbs. Abbreviation: ST Modes: Batch, Line or Full Screen |
| SUFFIX [ON OFF] |
| Function: Opens and closes the suffix area. Abbreviation: SUF Modes: Full Screen |
| SYSCMD |
| Function: Allows you to enter CMS commands. Abbreviation: None Modes: Line or Full Screen |
| TRACE [PARA ENTRY NAME OFF] [PRINT] |
| Function: Display a flow of program control. Abbreviation: T Modes: Batch, Line or Full Screen |
| VTRACE [number] |
| Function: Displays a dynamic program execution in full screen mode. Abbreviation: V Modes: Full Screen |
| WHEN when-name [item expression] [(command list)] |
| Function: Monitors each COBOL statement for a breakpoint if issued or a command list is executed. Abbreviation: WH Modes: Batch, Line or Full Screen |
| WHERE [PRINT] |
| Function: Displays the current statement number. Abbreviation: WHER Modes: Batch, Line or Full Screen |

SYS-ED[®]
19 West 34th Street
New York, NY 10001
Phone: 212-564-9147
Fax: 212-967-3498
E-mail: sales@syped.com
www.syped.com

| | | | |
|-----------------------------|--|----------------------------|---|
| CALL 212-564-9147 | CLICK www.syped.com | FAX 212-967-3498 | US Headquarters 19 West 34th Street New York, NY 10001-3006 |
|-----------------------------|--|----------------------------|---|