

## Xpediter/TSO Line Commands

- Programming Skills
- Programming Languages
- Utilities & Development Tools
- Operating Systems
- Telecommunications
- VSAM
- CICSs
- IMS
- DB2 UDB
- MQSeries
- WebSphere
- Productivity Management

To view our 150+ OS/390 and z/OS mainframe courses available, visit our web site at [www.mainframetrainingbysysed.us](http://www.mainframetrainingbysysed.us)

To view our entire list of 1000+ course offerings visit [www.sysed.com](http://www.sysed.com).

*Get on the  
Fast Track!*



TM

Command	Description
) , (n, ), ))n	Scrolls a line or block one or n columns to the left.
( , (n, ((, ((n	Scrolls a line or block one or n columns to the right.
:	Freezes the line at the current column position.
:n	Scrolls a line to column n.
A	Sets an AFTER breakpoint on a line.
B	Sets a BEFORE breakpoint on a line.
C, CC	Sets COUNT breakpoint(s) on a line or block.
D	On a PROCEDURE DIVISION line, deletes all breakpoints on the line. On a displayed line, removes the displayed value. On an inserted line, removes the line. On a kept line, removes the kept value. On an excluded range of lines, reshows all the excluded lines.
D:	On a frozen line, enables left and right scrolling.
DA	Deletes the AFTER breakpoint on a line.
DB	Deletes the BEFORE breakpoint on a line.
DC	Deletes the COUNT breakpoint on a line.
DD	Deletes all commands and breakpoints on a block of lines.
DE	Deletes the display of elementary values.
DG	Deletes the effect of the G or GG line command.
DH	Deletes the values displayed in hexadecimal format.
DS	Deletes the SKIP breakpoint on a line.
DT	Deletes the column template from above a displayed variable.
E, En, EE	Displays the elementary items for the first or n variable(s) on a line or block.
F, Fn	Reshows the first or n line(s) from a block of excluded lines.
G, GG	Expands macros or compressed EXEC code (GEN) on a line or block.
GT	Repositions (GOTO) the current execution pointer to a line.
H, Hn, HH	Displays the first or n variable(s) on a line or block in hexadecimal format.
I, In	Inserts one or n line(s) below the current line.
K, Kn, KK	Sets a KEEP for the first or n variable(s) on a line or block.
KE, KE n	Keeps the elementary items for the first or n variable(s) on a line or block.
KH, KH n	Keeps the first or n variable(s) on a line or block in hexadecimal format.
K*	Keeps all variables on a line.
L, Ln	Reshows the last or n line(s) from a block of excluded lines.
M	Displays memory starting from the address associated with a line.
P, Pn, PP	Temporarily displays (PEEK) the first or n variable(s) on a line or block.
PE, PE n	Displays the elementary items for the first or n variable(s) on a line or block.
PH, PH n	Displays the first or n variable(s) on a line or block in hexadecimal format.
S, SS	Sets a SKIP breakpoint(s) on a line or block.
T, TT	Displays a column template above a displayed or kept item or block.
X, XX	Excludes a line or block.
XP	Captures and displays EXPLAIN information about an EXEC SQL statement. Valid only with the XPEDITER for DB2 Extension.